

650 DEVICE MANAGER SOFTWARE

NOTE: This software has been tested for Windows XP.

- 1) Create a folder on the computer into which all the files will be placed.
- 2) Using an internet browser, go to Carmanah Partner Portal, login and download the .zip file into the folder
- 3) Double-click on the .zip file to unpack the seven (7) files that are in it. Do not run any of these files yet.
- 4) If you do not have the Microsoft .NET framework version 3.5 installed on your system, download and install it from [here](#).
- 5) Once the .NET Framework is installed on the computer, double-click on the file "61124RevCSetup.exe" to install the 650 Device Manager software.
- 6) When the 650 Device Manager software is installed, log in as "Distributor" using the password 3Sunlight5.
- 7) You will need a standard USB-to-Mini USB cable to connect the 650 light to any available USB port on the computer. These cables are common and can be obtained at any consumer electronics store.
- 8) Connect the 650 light to the computer.
- 9) When the 650 light is connected to the computer, the 650 Device Manager software will recognize the type and colour of 650 and show a corresponding image of the correct colour.

NOTE: At this time, users need to change their Regional Settings in XP to North America (e.g. English(Canada) or English(United States)) to ensure the program correctly interprets the meaning of periods and commas.

- 1) Click Start - Settings - Control Panel - Regional Settings and Language Options
- 2) Double click on "Regional and Language Options"
Under "Standards and Formats" on the first tab (by default), choose "English (Canada)"
- 3) Click OK
- 4) At this point, the 650 Device Manager can be started and it will operate correctly.
- 5) Once programming is completed, shut down Device Manager and again use the "Regional and Language Options" to return the computer to its original settings.

NOTE:

The 650 Device Manager is for Windows XP only. The Device Manager software does not work on Vista or Windows 7.

Also note that the 650 Device Manager operates normally in a computer whose Regional Settings use a period as the decimal point and a comma as the thousands separator. For example:

1,234.56

Countries that do not use this format, for example those that reverse the role of comma and period, will find that the 650 Device Manager does not produce meaningful results. Carmanah is creating a new version of the 650 Device Manager that corrects for this behaviour. Until the new version of the Device Manager software is available, Carmanah recommends the following process for countries affected by this:

- 1) Click Start -> Settings -> Control Panel -> Regional Settings and Language Options
- 2) Double-click on "Regional and Language Options"
- 3) Under "Standards and Formats" on the first tab (by default), choose "English (Canada)"
- 4) Click OK

At this point, the 650 Device Manager can be started and it will operate correctly. Once programming is completed, shut down Device Manager and again use the "Regional and Language Options" to return the computer to its original settings. After having done this once, Windows XP will place a button on the taskbar that allows for easy switching between regional settings.